



**BOX**<sup>SM</sup>  
TECHNOLOGY

**Automated Trade Reporting**  
**SOLA® ATR Specifications Guide**  
**for BOX**

***Confidential***

ATR-BX-001E  
Document Revision: 3.0  
Date of Issue: 2021-05-21



## Copyright

---

This document and all information contained herein is and will remain at all times proprietary and confidential information of BOX Technology.

No part of this document may be photocopied, reproduced, stored on retrieval system, or transmitted, in any form or by any means whether, electronic, mechanical, or otherwise without the prior written consent of BOX Technology.

The information included in this document is believed to be accurate. BOX Technology does not guarantee the completeness or accuracy of any information included herein. This document is produced with the understanding that BOX Technology is providing information and not in any way providing engineering or other professional services.

BOX Technology reserves the right to change details in this publication without notice.

ATR-BX-001E, Document Version 3.0

## Document History

---

VERSION	DATE	CHANGE DESCRIPTION
1.0	2003-04	First draft
1.1	2003-08	Changes in message type 30 & 31 New section on 'BOX Contacts' (sec. 7)
1.2		Add details in section 3. BOX-ATR Definition.
1.3	2005-08	Inserted changes to order origin codes in message type 30, 31, 35, 36, 40, 41, 45, 46 field 'Account Type' (RFC BX05-0029).
1.4	2005-10	Trader ID is added to the Sub Trader ID field in the ATR messages 30, 31, 35 and 36. (BX05-0080).
1.5	2006-01	5.2.9 Add V, W values to Account Type (RFC BX05-0016)
1.6	2006-03	Minor corrections
1.7	2007-02-07	Latest version placed on Intranet
1.8	2008-06-05	Conversion to FrameMaker Symbology Initiative Modifications. A new format will be used for the following message types: <ul style="list-style-type: none"> <li>• Message Type 30 - Trade</li> <li>• Message Type 31 - Trade Cancel</li> <li>• Message Type 35 - As Of Trade</li> <li>• Message Type 36 - As Of Trade Cancellation</li> <li>• Message Type 40 - Allocation</li> <li>• Message Type 41 - Allocation Cancel</li> <li>• Message Type 45 - As Of Trade Allocation</li> <li>• Message Type 46 - As Of Trade Allocation Cancel</li> </ul>
1.9	2009-03-11	<ul style="list-style-type: none"> <li>• Modifications to add Order Identification by the addition of new fields: Client Order ID, Client Memo with existing field Client Account Number.</li> <li>• Addition of a new field:Liquidity Status</li> </ul>
1.10	2010-08-13	<ul style="list-style-type: none"> <li>• Modifications pertaining to Give-Up functionality include the following (APPW): New field, TradeType added to the end of the following ATR Message Types 30, 31, 35, 36, 40, 41, 45, and 46</li> <li>• Four new message types: (Message Type 50 – GiveUp, Message Type 51 – GiveUpCancel, Message Type 55 – AsOfGiveUp, Message Type 56 – AsOfGiveUpCancel)</li> <li>• New message types have the same content as message type 30, plus new fields: GiveUpSource, GiveUpDestination, TradeType</li> <li>• Added definitions to TradeType values for messages 30 &amp; 31</li> </ul>

VERSION	DATE	CHANGE DESCRIPTION
1.11	2011-10-21	<ul style="list-style-type: none"> <li>Removed the field TradeType from the GiveUp Message Type 50 since field already included in the Trade Message Type 30 upon whose structure the GiveUp message type is based:</li> <li>Added values for Solicitation and Facilitation to Trade Type in the Trade Message Type 30. Allocation and Give-Up messages will also contain these values for Trade Type. <ul style="list-style-type: none"> <li>Added 'T: Professional Customer' to Account Type in the Trade Message Type 30</li> <li>Modification to increase field length of Message Header from 22 to 24 bytes.</li> </ul> </li> <li>Modification to increase field length from 3 to 4 bytes in the following message types and respective field names: Message Type 09, field Member Number, Message Type 30, fields CMTA Broker, Executing Broker, Message Type 50, fields GiveUpSource, GiveUpDestination</li> </ul>
1.12	2011-12-23	<ul style="list-style-type: none"> <li>Correction to value 'M' in field TradeType (Should be 'TPR Trade - A trade done by a Third Party Router')</li> </ul>
1.13	2013-02-26	Increase the field <i>TradeNumber</i> from 6 to 15 characters to accommodate the new <i>UniqueTradeId</i> field, in Message Type 30 – Trade, Message Type 31 - Trade Cancel, Message Type 35 - As of Trade, Message Type 36 - As of Trade Cancellation, Message Type 40 – Allocation, Message Type 41 - Allocation Cancel, Message Type 45 - As of Trade Allocation, Message Type 46 - As of Trade Allocation Cancel, Message Type 50 – GiveUp, Message Type 51 - GiveUp Cancel, Message Type 55 - As of GiveUp, Message Type 56 - As of GiveUp Cancel
2.0	2014-09-01	<ul style="list-style-type: none"> <li>Updated the definition of the field <i>Account Type</i> to the <i>Trade</i> Message type structure.</li> <li>Added the field <i>Opposite Account Type</i> to the <i>Trade</i> Message type structure.</li> <li>Updated the length of all messages.</li> </ul>
2.1	2017-01-20	<ul style="list-style-type: none"> <li>Floor Trade: Added a value to AtrTradeType (Section 3.5.9)</li> <li>Minor editing</li> </ul>
3.0	2021-05-21	<ul style="list-style-type: none"> <li>New Section 2.2 for ATR Protocol versions</li> <li>Drop-Copy give-up and allocation for Designated Firm (Section 2.1)</li> <li>Added new TradeType C - Cross and Qualified Contingent Cross Orders (Section 3.5.9)</li> <li>Added new Account Types (Y: Floor Broker Dealer, Z: Floor Market Maker) to fields Account Type and Opposite Account Types (Section 3.5.9)</li> <li>Added Participant Session Name to Trade message (Section 3.5.9)</li> <li>Defined new message structure for Give-up with addition of Participant Session name (Section 3.5.17)</li> <li>Adjusted size of trade, allocation, and give-up messages</li> <li>New Error code for "Invalid Signon" (Section 3.5.22)</li> <li>Added Protocol version in message sequence diagrams (Section 4)</li> </ul>

# Table of Contents

---

<b>Section 1</b>	<b>Introduction</b> .....	<b>5</b>
1.1	Objective .....	5
1.2	Scope .....	5
1.3	BOX Contact .....	5
<b>Section 2</b>	<b>Overview</b> .....	<b>6</b>
2.1	ATR Description .....	6
2.2	ATR Protocol.....	6
2.3	Communication .....	6
<b>Section 3</b>	<b>Messages</b> .....	<b>8</b>
3.1	Message List.....	8
3.2	Conventions .....	9
3.3	Messages Format .....	10
3.4	Message Header (24 bytes).....	11
3.5	Message Body .....	12
3.5.1	Message Type 00 – Start Of Day (24 bytes) .....	12
3.5.2	Message Type 01 – Start Of Day Ack (24 bytes) .....	12
3.5.3	Message Type 02 – Circuit Assurance (24 bytes) .....	13
3.5.4	Message Type 03 – Circuit Response (24 bytes).....	13
3.5.5	Message Type 04 – Restart Request (30 bytes) .....	14
3.5.6	Message Type 05 – Restart Accepted (24 bytes).....	14
3.5.7	Message Type 08 – End Of Trading (24 bytes).....	14
3.5.8	Message Type 09 – Client Signon (34 bytes).....	15
3.5.9	Message Type 30 – Trade (184 bytes).....	15
3.5.10	Message Type 31 – Trade Cancel (184 bytes).....	19
3.5.11	Message Type 35 – As Of Trade (184 bytes).....	19
3.5.12	Message Type 36 – As Of Trade Cancellation (184 bytes).....	19
3.5.13	Message Type 40 – Allocation (184 bytes).....	19
3.5.14	Message Type 41 – Allocation Cancel (184 bytes).....	19
3.5.15	Message Type 45 – As Of Trade Allocation (184 bytes) .....	19
3.5.16	Message Type 46 – As Of Trade Allocation Cancel (184 bytes) .....	19
3.5.17	Message Type 50 – Give-Up (192 bytes) .....	19
3.5.18	Message Type 51 – Give-Up Cancel (192 bytes).....	23
3.5.19	Message Type 55 – As Of Give-Up (192 bytes) .....	23
3.5.20	Message Type 56 – As Of Give-Up Cancel (192 bytes).....	23
3.5.21	Message Type 98 – Ack Message (24 bytes).....	23
3.5.22	Message Type 99 – Error Message (up to 104 bytes).....	24
3.6	End-Of-Text (ETX) .....	24
<b>Section 4</b>	<b>Connection Management</b> .....	<b>25</b>
4.1	Single TCP/IP Connection, Single ATR Logical Connection .....	25
4.2	Single TCP/IP Connection, Multiple ATR Logical Connections, Different Participants .....	26
4.3	Multiple TCP/IP Connection, Multiple ATR Logical Connections, Different Participants .....	27
<b>Section 5</b>	<b>Recovery Connection Management</b> .....	<b>29</b>
5.1	Single TCP/IP Connection, Single ATR Logical Connection .....	29

# Section 1 Introduction

---

The purpose of this document is to detail the specifications of the BOX Options Automated Trade Reporting (BOX-ATR) data feed.

## 1.1 Objective

The main objective of this Guide is to provide Participants with the functionality required to interact with the BOX Options Automated Trade Reporting (BOX-ATR) data feed.

## 1.2 Scope

This document includes:

- BOX-ATR service description
- Message format and definitions
- Connection management and recovery management flow

## 1.3 BOX Contact

Market Operations Center Support / Technical Help Desk  
Toll Free: 1-866-768- 8845  
[boxmoc@boxoptions.com](mailto:boxmoc@boxoptions.com)

## Section 2 Overview

---

### 2.1 ATR Description

The BOX-ATR consists of a private, real time feed containing transactions, give-ups, and allocations executed on BOX. The private feature allows firms to have active connections to the BOX-ATR Server receiving only the following trades:

- Trades (regular and 'As Of'), give-ups, and allocations in which they are the executing Participant
- Trades (regular and 'As Of'), give-ups, and allocations in which they are the Clearing Participant
- Give-Ups (regular and 'As Of') and allocations in which they are the receiving Participant of a give-up
- Give-Ups (regular) and allocations (regular) in which they are designated as Drop-Copy participants by the BOX Market Operations Center (MOC). Only one Drop-Copy Participant can be assigned per allocation or give-up.

Trades, give-ups, and allocations are on instruments traded only on BOX. These include the trades done on BOX to offset trades executed through third-party routers at an away exchange.

### 2.2 ATR Protocol

The ATR provides two protocols (A0 and A1):

- A0 protocol is the default protocol - please refer to the ATR Specifications Guide Version 2.1 for message structure
- A1 protocol is the protocol detailed in this document (Version 3.0)

### 2.3 Communication

The BOX-ATR service is provided through a standard TCP/IP communication link. A specific IP Port will be chosen by BOX for providing the BOX-ATR feed. The Participant must maintain a configuration that identifies the BOX-ATR Server IP Address, IP Port Number, and the Participant ID for Login.

**Note:** BOX-ATR service set-up, IP addresses, and IP Port Number must be obtained from BOX.

The BOX Participant is responsible for initiating communications with the BOX-ATR Server.

Each Participant must ensure that it has a configuration file to control the time and destination of the connection and is responsible for initiating the connection to the BOX-ATR server in a timely manner.



**Note:** The BOX-ATR server does not initiate any TCP/IP communications sessions with the BOX-ATR Participant.

After the BOX-ATR Participant has made the connection to the BOX-ATR Server, it must transmit a login message to identify and authenticate itself.

## Section 3 Messages

This section includes:

- Message List
- Message Format and Definitions

### 3.1 Message List

The following messages are supported in this version of the BOX-ATR data service feed.

MESSAGE NAME	MESSAGE TYPE	SOURCE	
		CLIENT (PARTICIPANT)	SERVER (BOX)
Start Of Day	00		X
Start Of Day ACK	01	X	
Circuit Assurance	02		X
Circuit Response	03	X	
Restart Request	04	X	
Restart Accepted	05		X
End Of Trading	08		X
Client Signon	09	X	X
Trade	30		X
Trade Cancel	31		X
As Of Trade	35		X
As Of Trade Cancel	36		X
Allocation	40		X
Allocation Cancel	41		X
As Of Trade Allocation	45		X
As Of Trade Allocation Cancel	46		X
GiveUp	50		X

MESSAGE NAME	MESSAGE TYPE	SOURCE	
		CLIENT (PARTICIPANT)	SERVER (BOX)
GiveUpCancel	51		X
AsOfGiveUp	55		X
AsOfGiveUpCancel	56		X
Ack Message	98	X	X
Error Message	99		X

## 3.2 Conventions

The notation convention for elements of the BOX-ATR specifications in the Data Type column are:

- N character means numeric values from 0 to 9
- A character means any US-ASCII alpha or numeric character
- Elements separated by a vertical line '|' are alternatives
- [blank] means one space (ASCII 32)

### 3.3 Messages Format

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES																																														
Message Header	24	A	Refer to Section – Message Header																																														
Body of message	Up to 155 bytes	N	<table border="0"> <thead> <tr> <th>Message Body</th> <th>Nbr. of Bytes</th> </tr> </thead> <tbody> <tr><td>00 Start Of Day</td><td>0</td></tr> <tr><td>01 Start Of Day Ack</td><td>0</td></tr> <tr><td>02 Circuit Assurance</td><td>0</td></tr> <tr><td>03 Circuit Response</td><td>0</td></tr> <tr><td>04 Restart Request</td><td>6</td></tr> <tr><td>05 Restart Accepted</td><td>0</td></tr> <tr><td>08 End Of Trading</td><td>0</td></tr> <tr><td>09 Client Signon</td><td>10</td></tr> <tr><td>30 Trade</td><td>147</td></tr> <tr><td>31 Trade Cancel</td><td>147</td></tr> <tr><td>35 As Of Trade</td><td>147</td></tr> <tr><td>36 As Of Trade Cancel</td><td>147</td></tr> <tr><td>40 Allocation</td><td>147</td></tr> <tr><td>41 Allocation Cancel</td><td>147</td></tr> <tr><td>45 As Of Trade Allocation</td><td>147</td></tr> <tr><td>46 As Of Trade Allocation Cancel</td><td>147</td></tr> <tr><td>50 Give Up</td><td>155</td></tr> <tr><td>51 Give Up Cancel</td><td>155</td></tr> <tr><td>55 As Of Give Up</td><td>155</td></tr> <tr><td>56 As Of Give Up Cancel</td><td>155</td></tr> <tr><td>98 Ack Message</td><td>0</td></tr> <tr><td>99 Error Message</td><td>80</td></tr> </tbody> </table>	Message Body	Nbr. of Bytes	00 Start Of Day	0	01 Start Of Day Ack	0	02 Circuit Assurance	0	03 Circuit Response	0	04 Restart Request	6	05 Restart Accepted	0	08 End Of Trading	0	09 Client Signon	10	30 Trade	147	31 Trade Cancel	147	35 As Of Trade	147	36 As Of Trade Cancel	147	40 Allocation	147	41 Allocation Cancel	147	45 As Of Trade Allocation	147	46 As Of Trade Allocation Cancel	147	50 Give Up	155	51 Give Up Cancel	155	55 As Of Give Up	155	56 As Of Give Up Cancel	155	98 Ack Message	0	99 Error Message	80
Message Body	Nbr. of Bytes																																																
00 Start Of Day	0																																																
01 Start Of Day Ack	0																																																
02 Circuit Assurance	0																																																
03 Circuit Response	0																																																
04 Restart Request	6																																																
05 Restart Accepted	0																																																
08 End Of Trading	0																																																
09 Client Signon	10																																																
30 Trade	147																																																
31 Trade Cancel	147																																																
35 As Of Trade	147																																																
36 As Of Trade Cancel	147																																																
40 Allocation	147																																																
41 Allocation Cancel	147																																																
45 As Of Trade Allocation	147																																																
46 As Of Trade Allocation Cancel	147																																																
50 Give Up	155																																																
51 Give Up Cancel	155																																																
55 As Of Give Up	155																																																
56 As Of Give Up Cancel	155																																																
98 Ack Message	0																																																
99 Error Message	80																																																
ETX	1	A	ASCII character 0x03																																														

### 3.4 Message Header (24 bytes)

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Source	4	A	Contains the mnemonic of the message source. BOX – For BOX or the firm's clearing number.
Destination	4	A	Contains the mnemonic of the message destination. BOX – For BOX or the firm's clearing number.
Message Type	2	N	00: Start of Day 01: Start of Day Ack 02: Circuit Assurance 03: Circuit Response 04: Restart Request 05: Restart Accepted 08: End of Trading 09: Client Signon 30: Trade 31: Trade Cancel 35: As Of Trade 36: As Of Trade Cancel 40: Allocation 41: Allocation Cancel 45: As Of Trade Allocation 46: As Of Trade Allocation Cancel 50: Give Up 51: Give Up Cancel 55: As Of GiveUp 56: As Of GiveUp Cancel 98: Ack Message 99: Error Message
Message Flag	1	A	R: Re-transmitted message D: Duplicated message blank: Normal message
Control Byte	1	A	Unused Always [blank]
Sequence Number	6	N	Official message number formatted by the sender. This number must be reset every morning to 1 and is normally incremented by one with each message sent. In the [1,999999] range, right justified, zero padded.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Ack Sequence Number	6	N	Original outbound number of the message for which this response or ACK is issued. In the [1,999999] range, right justified, zero padded.

### 3.5 Message Body

The message body contains the message type.

#### 3.5.1 Message Type 00 – Start Of Day (24 bytes)

This message is used to advise the other side about the initiation of application-to-application communication. This message must be acknowledged with a "START OF DAY ACK".

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header

#### 3.5.2 Message Type 01 – Start Of Day Ack (24 bytes)

This message is sent as acknowledgement to the START OF DAY and advises the BOX-ATR Server that it is ready to exchange messages.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header ACK SEQUENCE NUMBER must be the number of the START OF DAY message.

### 3.5.3 Message Type 02 – Circuit Assurance (24 bytes)

This message is sent by the BOX-ATR server to verify that the other side's application is running correctly. It is sent during the day at a fixed time interval (5 minutes). The receiver of this message should send a "circuit response" message within 3 minutes of receipt of this message. If the response is not detected within this time interval, then BOX-ATR server may treat this situation as a possible failure of the communications link or partner program and force a link disconnect. Note that the circuit assurance message may appear at any time during the session, even as part of the connection establishment handshake.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header The SEQUENCE NUMBER and ACK SEQUENCE NUMBER fields may contain zero to reduce the need for the client program to track these messages for retransmit or restart situations

### 3.5.4 Message Type 03 – Circuit Response (24 bytes)

This message is a response to a circuit assurance message. It should be returned promptly upon the receipt of the circuit assurance message.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header ACK SEQUENCE NUMBER must be the sequence number of the CIRCUIT ASSURANCE message. The Sequence number MUST be zero

### 3.5.5 Message Type 04 – Restart Request (30 bytes)

The BOX-ATR Participant application uses this to restart its communications session. When the BOX-ATR Participant sends this message, the body sequence number indicates which message number will be the first sent. When the BOX-ATR Participant sends a restart request, this number is used to request that the BOX-ATR server begin its restart at this sequence number. Once the restarted messages are sent, the BOX-ATR server will begin transmitting messages in the normal sequence.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header
Sequence Number	6	N	If the sequence number is higher than any message number known to the ATR server, it will use the last message known to it. In the [1,999999] range, right justified, zero padded

### 3.5.6 Message Type 05 – Restart Accepted (24 bytes)

This message is the normal response to a restart request message.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header ACK SEQUENCE NUMBER must be the message number of the RESTART REQUEST message.

### 3.5.7 Message Type 08 – End Of Trading (24 bytes)

This message is sent by BOX to advise firms about the end of trading. After the end of trading has been received, the BOX-ATR Participant may request retransmission of any messages it needs prior to the eventual shutdown of the ATR service for the business day.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header



### 3.5.8 Message Type 09 – Client Signon (34 bytes)

This message must be the first message sent by the BOX-ATR Participant after establishing (or re-establishing) its TCP/IP session with the server. If the initial sequence number is higher than any message number known to the ATR server, it will use the last message known to it.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header
Member Number	4	N	In the [0001,9999] range Right justified, zero padded
Initial Sequence Number	6	N	The ATR server will begin at this specific sequence number In the [1,999999] range Right justified, zero padded
Protocol Version	2	A	Protocol Version supported: A0, A1  If blank, A0 is selected as default protocol If this field is omitted, A0 is selected as default protocol If other value other than A0 or A1, A0 is selected as the default protocol

### 3.5.9 Message Type 30 – Trade (184 bytes)

Message sent by the BOX-ATR server that contains trade information.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header
Trade Number	15	A	Standard TradeId consisting of: Side field: only the first letter of the verb, i.e., "B" for Buy and "S" for Sell InstrumentId and GroupId field TradeId field
Transaction Type	1	A	Side of the trader in the present trade B: Buy S: Sell

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Timestamp	6	A	Time at which the trade occurred (Eastern Time) HHMMSS
Symbol	30	A	Instrument symbol Left justified, Blank padded
Expiration Date	6	A	Expiration date of the instrument YYMMDD
Strike Price	8	N	Option Strike Price The format is defined by the new field 'Strike Price Fraction Indicator'. Filled with zero when the instrument is not an option Right justified, Zero padded
Strike Price Fraction Indicator	1	A	Define the number of decimal places or fraction positions
Option Type	1	A	C: Call P: Put Blank: If not an option
Volume	8	N	Volume of the trade Right justified, Zero padded
Price (x 10000)	8	N	Transaction price Right justified, Zero padded
CMTA Broker	4	N	Contains the numeric portion of the BOX participant ID who will receive the trade in a CMTA
Account Type	1	A	Account type of the executing broker of the trade 6: Public Customer 7: Broker Dealer 8: Market Maker T: Professional Customer V: Floor Broker Customer W: Broker Dealer cleared as Customer X: Away Market Maker Y: Floor Broker Dealer Z: Floor Market Maker

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Sub-trader ID	3	A	For 'Allocation' (40), 'Allocation Cancel' (41), 'As of Allocation' (45), and 'As of Allocation Cancel' (46) messages, the 'Sub-trader ID' field contains the Market maker OCC sub-account. For 'Trade' (30), 'Trade Cancel' (31), 'As Of Trade' (35) and 'As Of Trade Cancel' (36) messages, the 'Sub-trader ID' field contains the last 2 digits of the Trader ID.
Open Close	1	A	Position of the trade O: Open C: Close
Executing Broker	4	N	Contains the numeric portion of the BOX participant ID executing the trade In the [0001,9999] range Right justified, zero padded
Client Account Number	12	A	Left justified, right blank filled Used with Client Order ID and Client Memo for Order Identification
Client Order ID.	20	A	Left justified, right blank filled Used with Client Account Number and Client Memo for Order Identification
Client Memo	16	A	Left justified, right blank filled Used with Client Account Number and Client Order ID for Order Identification
Liquidity Status	1	A	Possible values: ?: Unknown ' ': None M: Maker T: Taker

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
TradeType	1	A	Possible values: N: Normal – A regular trade O: CrossedOrders – A trade with the same Firm ID on both sides T: TraderCrossedOrders – A trade with the same Trader ID on both sides M: TPR Trade – A trade done by a Third Party Router P: PIP – A trade done at the end of a PIP auction F: FirmDo – A trade resulting from a Directed Order A: AsOf – A trade entered by the BOX MOC to correct a trade executed on a previous day E: Late – A trade entered by the BOX MOC to correct a trade executed on the same day S: Solicitation – A trade done as part of a Solicitation auction I: Facilitation – A trade done as part of a Facilitation auction R: FloorTrade C: Customer Cross Orders or Qualified Contingent Cross Orders
Opposite Account Type	1	A	Account type of the opposite executing broker of the trade 6: Public Customer 7: Broker Dealer 8: Market Maker T: Professional Customer V: Floor Broker Customer W: Broker Dealer cleared as Customer X: Away Market Maker Y: Floor Broker Dealer Z: Floor Market Maker
Participant Session Name	12	A	Session Name of the Participant who executed the trade <ul style="list-style-type: none"> <li>• Filled for Regular (Trade, Trade Cancel, Allocation and Allocation Cancel)</li> <li>• Empty for As-Of (Trade, Trade Cancel, Allocation and Allocation Cancel)</li> </ul>

### 3.5.10 **Message Type 31 – Trade Cancel (184 bytes)**

Message sent by the BOX-ATR server that contains transaction cancellation information. Use the same structure as the trade message type.

### 3.5.11 **Message Type 35 – As Of Trade (184 bytes)**

Message sent by the BOX-ATR server that contains 'As Of Trade' information. Use the same structure as the trade message type.

### 3.5.12 **Message Type 36 – As Of Trade Cancellation (184 bytes)**

Message sent by the BOX-ATR server that contains 'As Of Trade' cancellation information. Use the same structure as the trade message type.

### 3.5.13 **Message Type 40 – Allocation (184 bytes)**

Message sent by the BOX-ATR server that contains allocation information. Use the same structure as the trade message type.

### 3.5.14 **Message Type 41 – Allocation Cancel (184 bytes)**

Message sent by the BOX-ATR server that contains allocation cancel information. Use the same structure as the trade message type.

### 3.5.15 **Message Type 45 – As Of Trade Allocation (184 bytes)**

Message sent by the BOX-ATR server that contains 'As Of Trade' allocation information. Use the same structure as the trade message type.

### 3.5.16 **Message Type 46 – As Of Trade Allocation Cancel (184 bytes)**

Message sent by the BOX-ATR server that contains 'As Of Trade' allocation cancel information. Use the same structure as the trade message type.

### 3.5.17 **Message Type 50 – Give-Up (192 bytes)**

Message sent by the BOX-ATR server that contains give-up information.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section 3.4

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Trade Number	15	A	Standard TradeId consisting of: Side field: only the first letter of the verb, i.e., "B" for Buy and "S" for Sell InstrumentId and GroupId field TradeId field
Transaction Type	1	A	Side of the trader in the present trade B: Buy S: Sell
Timestamp	6	A	Time at which the trade occurred (Eastern Time) HHMMSS
Symbol	30	A	Instrument symbol Left justified, Blank padded
Expiration Date	6	A	Expiration date of the instrument YYMMDD
Strike Price	8	N	Option Strike Price The format is defined by the new field 'Strike Price Fraction Indicator.' Filled with zero when the instrument is not an option Right justified, Zero padded
Strike Price Fraction Indicator	1	A	Define the number of decimal places or fraction positions
Option Type	1	A	C: Call P: Put Blank: If not an option
Volume	8	N	Volume of the trade Right justified, Zero padded
Price (x 10000)	8	N	Transaction price Right justified, Zero padded
CMTA Broker	4	N	Contains the numeric portion of the BOX participant ID who will receive the trade in a CMTA deal.
Account Type	1	A	Account type of the executing broker of the trade 6: Public Customer 7: Broker Dealer

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
			8: Market Maker T: Professional Customer V: Floor Broker Customer W: Broker Dealer cleared as Customer X: Away Market Maker Y: Floor Broker Dealer Z: Floor Market Maker
Sub-trader ID	3	A	For 'GiveUp' (50), 'GiveUp Cancel' (51), 'As Of GiveUp' (55) and 'As Of GiveUp Cancel' (56) messages, the 'Sub-trader ID' field contains the Market maker OCC sub-account.
Open Close	1	A	Position of the trade O: Open C: Close
Executing Broker	4	N	Contains the numeric portion of the BOX participant ID executing the trade In the [0001,9999] range Right justified, zero padded
Client Account Number	12	A	Left justified, right blank filled Used with Client Order ID and Client Memo for Order Identification
Client Order ID.	20	A	Left justified, right blank filled Used with Client Account Number and Client Memo for Order Identification
Client Memo	16	A	Left justified, right blank filled Used with Client Account Number and Client Order ID for Order Identification
Liquidity Status	1	A	Possible values: ? : Unknown '': None M: Maker T: Taker

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
TradeType	1	A	<p>Possible values:</p> <p>N: Normal – A regular trade</p> <p>O: CrossedOrders – A trade with the same Firm ID on both sides</p> <p>T: TraderCrossedOrders – A trade with the same Trader ID on both sides</p> <p>M: TPR Trade – A trade done by a Third Party Router</p> <p>P: PIP – A trade done at the end of a PIP auction</p> <p>F: FirmDo – A trade resulting from a Directed Order</p> <p>A: AsOf – A trade entered by the BOX MOC to correct a trade executed on a previous day</p> <p>E: Late – A trade entered by the BOX MOC to correct a trade executed on the same day</p> <p>S: Solicitation – A trade done as part of a Solicitation auction</p> <p>I: Facilitation – A trade done as part of a Facilitation auction</p> <p>R: FloorTrade</p> <p>C: Customer Cross Orders or Qualified Contingent Cross Orders</p>
Opposite Account Type	1	A	<p>Account type of the opposite executing broker of the trade</p> <p>6: Public Customer</p> <p>7: Broker Dealer</p> <p>8: Market Maker</p> <p>T: Professional Customer</p> <p>V: Floor Broker Customer</p> <p>W: Broker Dealer cleared as Customer</p> <p>X: Away Market Maker</p> <p>Y: Floor Broker Dealer</p> <p>Z: Floor Market Maker</p>
GiveUpSource	4	A	Firm ID that is giving up the trade, as per the same field defined in the Give-Up Agreement.
GiveUpDestination	4	A	Firm ID to which the trade is given up, as per the same field defined in the Give-Up Agreement.
Participant Session Name	12	A	<p>Session Name of the Participant who executed the trade.</p> <ul style="list-style-type: none"> <li>Filled for Source Participant executing the GiveUp and GiveUp Cancel</li> </ul>



FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
			<ul style="list-style-type: none"> <li>• Empty for Destination Participant receiving the GiveUp and GiveUp Cancel</li> <li>• Empty for As-Of (GiveUp and GiveUp Cancel)</li> </ul>

### 3.5.18 Message Type 51 – Give-Up Cancel (192 bytes)

Message sent by the BOX-ATR server that contains Give-Up Cancel information. Use the same structure as the Give-Up message type.

### 3.5.19 Message Type 55 – As Of Give-Up (192 bytes)

Message sent by the BOX-ATR server that contains 'As Of Give-Up' information. Use the same structure as the Give-Up message type.

### 3.5.20 Message Type 56 – As Of Give-Up Cancel (192 bytes)

Message sent by the BOX-ATR server that contains 'As Of Give-Up Cancel' information. Use the same structure as the Give-Up message type.

### 3.5.21 Message Type 98 – Ack Message (24 bytes)

This message is sent as an acknowledgement of another message. This acknowledgement is sent only for messages with the control byte flag set (value = "Y") in its header.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header

### 3.5.22 Message Type 99 – Error Message (up to 104 bytes)

Message sent by the BOX-ATR server when an error occurs on a message received from a firm.

FIELD NAME	LENGTH (BYTES)	DATA TYPE	DEFINITION / VALIDATION RULES
Message Header	24		Refer to Section – Message Header ACK SEQUENCE NUMBER must be the number of the message that is in error
Error Text	80	A	Refer to Error Codes Contains the error description.

#### Error Codes

The following table displays the error text that will appear in error responses.

ERROR TEXT	DESCRIPTION
Invalid message type	The message type provided in the header message is invalid.
Invalid firm identifier	The firm identifier provided in the header message is invalid. The firm identifier must be configured in the system so the BOX-ATR server may recognize them.
Invalid sequence number	The value of the 'Sequence Number' field in the header message is not a numeric. The value of the 'Sequence Number' field in the Restart Request message is not a numeric .
Invalid sequence	The received message is out of sequence.
Not Signon	The Signon message is invalid. No valid Signon message has been received.
Invalid Signon	The firm is not configured to connect to the ATR server. Please contact Market Operations Center (MOC).

### 3.6 End-Of-Text (ETX)


An End-of-Text (ETX) ASCII character must follow each TCP/IP message sent or received by the BOX-ATR server. This delimiter character is hexadecimal 03 (0x03) and must appear only at the end of the message content.

## Section 4 Connection Management

This section presents several examples of connection management flow.


### 4.1 Single TCP/IP Connection, Single ATR Logical Connection


Trade and Trade Cancel messages for Participant 'ABCD' are sent over one TCP/IP connection and on one ATR logical connection.



## 4.2 Single TCP/IP Connection, Multiple ATR Logical Connections, Different Participants


Trade and Trade Cancel messages for Participant 'ABCD' and 'EFGH' are sent simultaneously over the same TCP/IP connection, but on different ATR logical connections - each having their own sequence number.






### 4.3 Multiple TCP/IP Connection, Multiple ATR Logical Connections, Different Participants

Trade and Trade Cancel messages for Participant 'ABCD' and 'EFGH' are sent simultaneously over different TCP/IP connections, and on different ATR logical connections - each having their own sequence number.






## Section 5 Recovery Connection Management

This section includes a recovery connection flow example.

### 5.1 Single TCP/IP Connection, Single ATR Logical Connection

Trade and Trade Cancel messages for Participant 'XXXX' are sent over one TCP/IP connection and on one ATR logical connection.



**Note:** For situations where there are more than one TCP/IP connections and more than one ATR logical connections, refer to [Section 4](#).



**BOX**<sup>SM</sup>  
TECHNOLOGY

**BOX Technology.**

2000 Mansfield St Suite 510,  
Montreal, Quebec, H3A 2Z6  
Canada